

HTC Configuration Guide Windows Mobile 6

GPRS Internet

Settings Overview

Macquarie Vodafone Access Point: vfinternet.au

Macquarie Telstra Access Point: telstra.wap OR mdata.net.au

Configuration Guide

GPRS will be setup when you first turn the phone on with a sim card installed

1. Select Yes to the connection setup prompt, It may take a minute to show, the device will now do the setup
2. Click Restart when prompted

Manual Setup

1. Select the Start > Settings
2. Select the Connections Tab > Connection Setup
3. Country: Australia
4. Operator: Whichever the user will be on.
5. Select OK
6. Select Yes
7. Select Restart

HTC Configuration Guide Windows Mobile 6

Outlook Email

Settings Overview

Email address: Your University address (eg. firstname.lastname@adelaide.edu.au)

Username: Your University login (eg. a1234567)

Password: Your University password

Mail server type: IMAP4

Incoming mail server: mail.adelaide.edu.au

Outgoing mail server (Vodafone): smtp.vodafone.net.au

Outgoing mail server (Telstra): mail.bigpond.com

Configuration Guide

1. Select Start > Messaging
2. Select New E-mail Account
3. Enter your E-mail address (eg. john.smith@adelaide.edu.au)
4. Uncheck automatic configuration
5. Select Next
6. Your E-Mail Provider: Internet E-mail
7. Select Next
8. Your Name: Enter the name you wish displayed on your E-mail messages (eg. John Smith)
9. Account display name: Enter the name you want the account to be called (eg. Uni Mail)
10. Select Next
11. Incoming mail server: mail.adelaide.edu.au
12. Account type: IMAP4
13. Select Next
14. User name: Enter your University user name (eg. a1234567)
15. Password: Enter your University password
16. Select Next
17. Outgoing (SMTP) mail server:
 - I. Vodafone enter smtp.vodafone.net.au
 - II. Telstra enter mail.bigpond.com
18. Uncheck the "Outgoing server requires authentication" box
19. Select Next
20. Automatic Send/Receive: Set the automatic Send/Receive to desired period
21. Select Finish

HTC Configuration Guide Windows Mobile 6

Synthesis SyncML

Install Files

[For Touch-screen devices \(eg. Palm Treo 750, Dopod 838pro, o2 Atom\)](#)

[For non Touch-screen devices \(eg. Imate Smartflip\)](#)

Install Procedure

1. Ensure Microsoft Activesync is installed on the PC
2. You can find the installation file for Windows XP & prior machines located <http://www.microsoft.com/windowsmobile/en-us/help/synchronize/activesync45.mspx>
3. Connect the device to the PC via the supplied USB cable
4. Browse to My Computer > Mobile Device
5. Download the appropriate install file from the links above
6. On your device, Select the Start > Programs > File Explorer
7. Select the "syncml_std_en.PPCWM.CAB" file
8. Select Yes button when requested to confirm installation
9. Select OK

Settings Overview

Server URL: <http://webcalendar.adelaide.edu.au:80/ocst-bin/ocas.fcgi>

Username: Your University logon (eg. a1234567)

Password: Your University password

Contacts/Events/Tasks Sync Mode: Slow

Contacts Server Path: ./contacts

Events Server Path: ./calendar/events

Tasks Server Path: ./calendar/tasks

Configuration of SyncML

1. Select the Start > Programs > Synthesis SyncML
2. Tick the Events box
 - If you wish to synchronise them, tick the Contacts and Tasks boxes.
3. Select Extras > Settings

HTC Configuration Guide Windows Mobile 6

4. SyncML Server address (URL): <http://webcalendar.adelaide.edu.au:80/ocst-bin/ocas.fcgi>
5. User name: Enter your University user name (eg. a1234567).
6. Password: Enter your University password.
7. Select the Organizer Tab
8. Contacts
 - I. Sync Mode: Slow
 - II. Server Path: ./contacts
9. Events
 - I. Sync Mode: slow
 - II. Server Path: ./calendar/events
 - III. Only From: Checked
 - IV. Days before: suggested period is 7 days
 - V. Days after: suggested period is 14 days
10. Tasks
 - I. Sync Mode: slow
 - II. Server Path: ./calendar/tasks
11. Select the Options Tab
12. Server Version: Automatic
13. Use Connection's Proxy: Checked
14. Select OK
15. Select Extra > Connection Settings
16. Preferred Connection when mobile: The Internet
17. Preferred Connection when in cradle: Automatic
18. Select OK
19. Select the Sync Icon (Bottom left)

Note: If SyncML will not sync then you may need to restart the phone.